

MENIUL <PLAY>

Funcțiile acestui meniu servesc la modul de redare audio a partiturii scrise. În mare parte aceste funcții sunt explicite de aceea nu vom insista prea mult decât asupra unuia singure.

[Playback devices] – dispozitive de redare audio

Sibelius folosește interfețele audio MIDI și ASIO instalate în computer. Fără a intra în detalii, acestea pot fi accesate de program, dar acesta trebuie să „știe” ce anume să facă cu ele. Toți parametri pot fi fixați prin intermediul ferestrei deschise de opțiunea [Playback devices]. După cum se vede această fereastră conține două tab-uri: Playback Devices (dispozitive de redare audio) și Input devices (Dispozitive de introducere a datelor, în cazul nostru tastatura MIDI) .

Sibelius - Meniul Play

Written by Ciprian Gabriel Pop
Monday, 02 January 2012 21:18 -

Playback and Input Devices

Playback Devices | **Input Device**

Click each playback device's Test button to see if you can hear it.

Set Use to Yes for one device and No for the others (unless you know you can use more than one at once). Also set Sound Set to the device name or type (e.g. General MIDI).

| Device | Test | Use | Sound Set | Latency (ms) |
|---------------------------------|------|-----|----------------|--------------|
| Kontakt Player | Test | Yes | Kontakt Silver | 8 |
| YAMAHA CBX.A Driver | Test | No | General MIDI | 0 |
| Out Audiophile USB | Test | No | General MIDI | 0 |
| Microsoft GS Wavetable SW Synth | Test | No | General MIDI | 0 |

Send program changes early

Kontakt Player Options...

Change settings for Kontakt Player (if installed).

Play in Background...

Change whether Sibelius should continue playing when you are using other programs.

Find New Devices

Play in Background

This lets you choose whether Sibelius is allowed to play, and control your MIDI devices, when it's not the foreground program.

Sibelius Owns MIDI Devices _____

- Never
 When in foreground
 Always

But don't play when in background

Cancel

OK

Meniul **Play** este folosit pentru a configura dispozitivele MIDI și pentru a alege dispozitivul de redare. În acest moment, dispozitivul de redare este „în față” adică lucrăm la

Sibelius - Meniul Play

Written by Ciprian Gabriel Pop
Monday, 02 January 2012 21:18 -

Playback and Input Devices

Playback Devices | **Input Device**

1. Highlight your input device, e.g. MIDI keyboard. (Typically this is the name of the port your keyboard is plugged in to.)

2. Try playing on your MIDI keyboard (or other input device): this indicator should light up.

3. MIDI Thru is for input devices which are silent (e.g. a master keyboard). It plays through one of your playback devices instead. Switch it off if your input device is not silent.

Click Find New Devices if one or more expected input devices is missing from the list above.

MIDI Guitar Channels

Input device is a guitar that outputs one MIDI channel per string

Number of strings:

4

6

MIDI channel of highest pitched string:

Omit Wrong Notes

Only notate:

Pitches sounding between

Lowest: Highest:

Notes with velocities higher than

(0 - 127) Test

Notes longer than

ticks; 256 ticks = 1 quarter note (crotchet)

Find New Devices OK

© 2012 Sibelius Software Ltd. All rights reserved. Sibelius is a registered trademark of Sibelius Software Ltd. Yamaha CBX is a registered trademark of Yamaha Corporation.